
eyewitness Documentation

Release 1.2.1

ching-hua, yang

Jan 29, 2020

Contents

1	Contents	3
1.1	Quick Start	3
1.2	ImageId	7
1.3	Image Utils	8
1.4	Object Detector	10
1.5	Detection Utils	10
1.6	Detection Result Filter	11
1.7	Evaluation Utils	12
1.8	A BboxMAPEvaluator Example	12
1.9	Audience Id	12
1.10	Feedback Msg Utils	13
1.11	Handler Example	14
1.12	ORM DB Models	16
1.13	DataSet Utils	18
1.14	MOT Module	20
	Python Module Index	23
	Index	25

Eyewitness is light weight framework for object detection application

naive schema

CHAPTER 1

Contents

1.1 Quick Start

a naive fake example including:

- ImageProducer (generate image)
- ObjectDetector (generate detection result: detected objects on the image)
- DetectionResultHandler(write the detection result to db)

we will provide a fake image producer, object_detector in following code.

1.1.1 Pre-requirement

install eyewitness

```
pip install eyewitness
```

download the pikachu image as pikachu.png

```
wget -O pikachu.png https://upload.wikimedia.org/wikipedia/en/a/a6/Pok%C3%A9mon_  
%20Pikachu_art.png
```



1.1.2 Implement a pikachu ImageProducer

keep yielding a pikachu image

```
import time
import arrow
from eyewitness.image_id import ImageId
from eyewitness.image_utils import Image
from eyewitness.config import IN_MEMORY
from eyewitness.image_utils import ImageHandler, ImageProducer

class InMemoryImageProducer(ImageProducer):
    def __init__(self, image_path, channel='pikachu', interval_s=3):
        self.pikachu = ImageHandler.read_image_file(image_path)
        self.interval_s = interval_s
        self.channel = channel

    def produce_method(self):
        return IN_MEMORY

    def produce_image(self):
        while True:
            image_id = ImageId(channel=self.channel, timestamp=arrow.now().timestamp,
                                file_format='png')
            image_obj = Image(image_id, pil_image_obj=self.pikachu)
            yield image_obj
            time.sleep(self.interval_s)
```

1.1.3 Implement a fake ObjectDetector

always detect and draw bbox at same place

```

import os
from pathlib import Path

from eyewitness.object_detector import ObjectDetector
from eyewitness.detection_utils import DetectionResult
from eyewitness.config import (
    BBOX,
    BoundedBoxObject,
    DRAWN_IMAGE_PATH,
    IMAGE_ID,
    DETECTED_OBJECTS,
    DETECTION_METHOD
)

class FakePikachuDetector(ObjectDetector):
    def __init__(self, enable_draw_bbox=True):
        self.enable_draw_bbox = enable_draw_bbox

    def detect(self, image_obj):
        """
        fake detect method for FakeObjDetector

        Parameters
        -----
        image_obj: eyewitness.image_utils.Image

        Returns
        -----
        DetectionResult

        """
        image_dict = {
            IMAGE_ID: image_obj.image_id,
            DETECTED_OBJECTS: [
                BoundedBoxObject(*[15, 15, 250, 225, 'pikachu', 0.5, ''])
            ],
            DETECTION_METHOD: BBOX
        }
        if self.enable_draw_bbox:
            image_dict[DRAWN_IMAGE_PATH] = str(
                Path(Path.cwd(), '%s_out.png' % image_obj.image_id))
            ImageHandler.draw_bbox(image_obj.pil_image_obj, image_dict[DETECTED_
            ↪OBJECTS])
            ImageHandler.save(image_obj.pil_image_obj, image_dict[DRAWN_IMAGE_PATH])

        detection_result = DetectionResult(image_dict)
        return detection_result

```

1.1.4 We can now run a fake example

always detect and draw bbox at same place

```

from eyewitness.result_handler.db_writer import BboxPeeweeDbWriter
from peewee import SqliteDatabase
import arrow

```

(continues on next page)

(continued from previous page)


```
# init InMemoryImageProducer
image_producer = InMemoryImageProducer('pikachu.png')

# init FakePikachuDetector
object_detector = FakePikachuDetector()

# prepare detection result handler
database = SqliteDatabase("example.sqlite")
bbox_sqlite_handler = BboxPeeweeDbWriter(database)

for image_obj in image_producer.produce_image():
    # generate the image_obj
    bbox_sqlite_handler.register_image(image_obj.image_id, {}) # register the image_
    ↪info
    detection_result = object_detector.detect(image_obj)
    bbox_sqlite_handler.handle(detection_result) # insert detection bbox result
```

which will keep generating pikachu image, and write detection result into db



1.1.5 Real Detector Implement with Yolov3

start with the yolov3 [Implement](#)

the repo implements:

- `naive_detector.py`: wrapper the detector
- `eyewitness_evaluation.py`: run a evaluation example
- `end2end_detector.py`: a end2end detector example with webcam
- `detector_with_flask.py`: a end2end detector example with flask server

a [naive detector](#) example

```

class YoloV3DetectorWrapper(ObjectDetector):
    def __init__(self, model_config, threshold=0.5):
        self.core_model = YOLO(**vars(model_config))
        self.threshold = threshold

    def detect(self, image_obj) -> DetectionResult:
        (out_boxes, out_scores, out_classes) = self.core_model.predict(image_obj.pil_
→image_obj)
        detected_objects = []
        for bbox, score, label_class in zip(out_boxes, out_scores, out_classes):
            label = self.core_model.class_names[label_class]
            y1, x1, y2, x2 = bbox
            if score > self.threshold:
                detected_objects.append(BoundingBoxObject(x1, y1, x2, y2, label, score,
→''))
        image_dict = {
            'image_id': image_obj.image_id,
            'detected_objects': detected_objects,
        }
        detection_result = DetectionResult(image_dict)
        return detection_result

```

also there is a docker example in the docker/yolov3_pytorch

1.1.6 Docker examples

more with real detector examples with docker here

1.2 ImageId

a module used to represent a image, and store image information

class eyewitness.image_id.ImageId(channel, timestamp, file_format='jpg')
Bases: object

ImageId is used to standardize the image_id format

Parameters

- **channel** (str) – channel of image comes
- **timestamp** (int) – timestamp of image arrive time
- **format** (str) – type of image

classmethod **from_str**(image_id_str)

serialize image_id from string, the separator of image is double dash –

Parameters **image_id_str** (str) – a string with pattern {channel}-{timestamp}–{fileformat}

e.g: "channel-12345567-jpg" (separated by a double dash)

Returns **image_id** – a ImageId obj

Return type **ImageId**

```
class eyewitness.image_id.ImageRegister
Bases: object

insert_image_info(raw_image_path)
    abstract method which need to be implement: how to insert/record image information

Parameters
    • image_id (ImageId) – ImageId obj
    • raw_image_path (str) – the path of raw image

register_image(image_id, meta_dict)
    interface for ImageRegister to register_image
```

1.3 Image Utils

Util methods for operation on image

```
class eyewitness.image_utils.Image(image_id, raw_image_path=None, pil_image_obj=None)
Bases: object
```

Image object is use to represent a Image in whole eyewitness project

To initialize a Image obj, image_id is required, and one of raw_image_path, pil_image_obj should be given, while only giving raw_image_path is kind of lazy evaluation, will read the image only when image_obj.pil_image_obj called

Parameters

- image_id (ImageId) – the id of image
- raw_image_path (Optional[str]) – the raw image path
- pil_image_obj (Optional[PIL.Image.Image]) – the pil image obj

fetch_bbox_pil_objs(bbox_objs)

Parameters

- bbox_objs (List[BoundingBoxObject]) – List of bbox objs, which used to generate bbox pil_image_obj
- Returns –
- ----- –
- output_list (List[PIL.Image.Image]) –

pil_image_obj

pil_image_obj is a property of the Image, if _pil_image_obj exist will directly return the obj, else will read from raw_image_path.

```
class eyewitness.image_utils.ImageHandler
Bases: object
```

util functions for image processing including: save, read from file, read from bytes, draw bounding box.

```
classmethod draw_bbox(image, detections, colors=None, font_path='/home/docs/checkouts/readthedocs.org/user_builds/
Medium.otf')
    draw bbox on to image.
```

Parameters

- **image** (*PIL.Image.Image*) – image to be draw
- **detections** (*List[BoundedBoxObject]*) – bbox to draw
- **colors** (*Optional[dict]*) – color to be used
- **font_path** (*str*) – font to be used

classmethod **read_image_bytes** (*image_byte*)
 PIL.Image.open support BytesIO input.

Parameters **image_path** (*BytesIO*) – read image from BytesIO obj

Returns **pil_image_obj** – PIL.Image.Image instance

Return type PIL.Image.Image

classmethod **read_image_file** (*image_path*)
 PIL.Image.open read from file.

Parameters **image_path** (*str*) – source image path

Returns **pil_image_obj** – PIL.Image.Image instance

Return type PIL.Image.Image

classmethod **save** (*image, output_path*)

Parameters

- **image** (*PIL.Image*) – image obj
- **output_path** (*str*) – path to be save

class eyewitness.image_utils.**ImageProducer**
 Bases: object

ImageProducer abstract class, should produce_method property and produce_image function

produce_image ()

produce_method

class eyewitness.image_utils.**PostBytesImageProducer** (*host, protocol='http'*)
 Bases: *eyewitness.image_utils.ImageProducer*

PostBytes Image Producer, will sent the image bytes to destination by Http post

produce_image (*image_id, image_bytes, raw_image_path=None*)

produce_method

class eyewitness.image_utils.**PostFilePathImageProducer** (*host, protocol='http'*)
 Bases: *eyewitness.image_utils.ImageProducer*

PostFilePath Image Producer, will sent the image_path string to destination by Http post

produce_image (*image_id, raw_image_path*)

produce_method

eyewitness.image_utils.**resize_and_stack_image_objs** (*resize_shape, pil_image_objs*)
 resize images and concat into numpy array

Parameters

- **resize_shape** (*tuple[int]*) – the target resize shape (w, h)
- **pil_image_objs** (*List[PIL.Image.Image]*) – List of image objs

Returns `batch_images_array`

Return type `np.array` with shape (n, w, h, c)

`eyewitness.image_utils.swap_channel_rgb_bgr(image)`

reverse the color channel image: convert image (w, h, c) with channel rgb -> bgr, bgr -> rgb.

Parameters `image (np.array)` –

Returns `image`

Return type `np.array`

1.4 Object Detector

a module define the object detector interface

`class eyewitness.object_detector.ObjectDetector`

Bases: `object`

Abstract class used to wrapper object detector

detect (`image_obj`)

[abstract method] need to implement detection method which return `DetectionResult` obj

Parameters `image_obj (eyewitness.image_util.Image)` –

Returns `DetectionResult` – the detected result of given image

Return type `DetectionResult`

detection_method

detection_method for the ObjectDetector is BBOX

Returns `detection_method`

Return type `String`

valid_labels

[abstract property] the valid_labels of this detectot e.g. `set(['person', 'pikachu' ...])` this will be used while want to evaluation the detector

Returns `valid_labels`

Return type `set[String]`

1.5 Detection Utils

Utils modules used for detection

`class eyewitness.detection_utils.DetectionResult (image_dict)`

Bases: `object`

represent detection result of a image.

Parameters `image_dict (dict)` –

- `detection_method`: `detection_method` str
- `detected_objects`: `List[tuple]`, list of detected obj (optional)
- `drawn_image_path`: str, path of drawn image (optional)

- `image_id`: `image_id` obj

`detected_objects`
List of detected objects in the image

Type `List[object]`

`drawn_image_path`
`drawn_image_path`

Type `str`

`classmethod from_json(json_str)`

`image_id`
`image_id` obj

Type `ImageId`

`to_json_dict()`

Returns `image_dict` – the dict representation of `detection_result`

Return type `dict`

class `eyewitness.detection_utils.DetectionResultHandler`
Bases: `object`

a abstract class design to handle detection result need to implement:

- `function: _handle(self, detection_result)`
- `property: detection_method`

`detection_method`

`handle(detection_result)`
wrapper of `_handle` function with the check of `detection_method` with `detection_result`.

Parameters `detection_result` (`DetectionResult`) –

1.6 Detection Result Filter

Utils modules used for filter detection result

class `eyewitness.detection_result_filter.DetectionResultFilter`
Bases: `object`

`apply(detection_result)`

`detection_method`

class `eyewitness.detection_result_filter.FeedbackBboxDeNoiseFilter` (`database,`
`de-`
`cay=0.9,`
`iou_threshold=0.7,`
`col-`
`lect_feedback_period=172800,`
`detec-`
`tion_threshold=0.5,`
`time_check_period=None`)

Bases: `eyewitness.detection_result_filter.DetectionResultFilter`

a Bbox DeNoise filter, which will read false alert bbox from tables: FalseAlertFeedback, BboxDetectionResult, and apply filter onto the detection result

check_proxy_db()
check if the db proxy is correct one, if not initialize again.

detection_method

String BBOX

Type detection_method

update_false_alert_feedback_bbox()
collect_bbox_false_alert_information

1.7 Evaluation Utils

used to calculate the detector performance currently support mAP for object detection

```
class eyewitness.evaluation.BboxMAPEvaluator(iou_threshold=0.5,
                                              dataset_mode='TEST_ONLY',
                                              logging_frequency=100)
Bases: eyewitness.evaluation.Evaluator
evaluate the bbox mAP score
static calculate_average_precision(recall, precision)
calculate_label_ap(valid_labels, detected_objs, gt_objs, gt_label_count)
refactor the evaluation from https://github.com/rafaelpadilla/Object-Detection-Metrics
evaluation_method
class eyewitness.evaluation.Evaluator
Bases: object
evaluate(detector, dataset)
evaluation_method
```

1.8 A BboxMAPEvaluator Example

```
# a evaluation example with yolov3 detector
# https://github.com/penolove/keras-yolo3/blob/eyeWitnessWrapper/eyewitness\_evaluation.py
from eyewitness.config import DATASET_TEST_ONLY
dataset_folder = 'VOC2007'
dataset_VOC_2007 = BboxDataSet(dataset_folder, 'VOC2007')
object_detector = YoloV3DetectorWrapper(args, threshold=0.0)
bbox_map_evaluator = BboxMAPEvaluator(dataset_mode=DATASET_TEST_ONLY)
# which will lead to ~0.73
print(bbox_map_evaluator.evaluate(object_detector, dataset_VOC_2007) ['mAP'])
```

1.9 Audience Id

a module used to represent a audience, and store audience information

```
class eyewitness.audience_id.AudienceId(platform_id, user_id)
Bases: object

the target of AudienceId is used to standardize the AudienceId format,
```

Parameters

- **platform_id**(str) – platform_id of feedback user from
- **user_id**(str) – id of feedback user

```
classmethod from_str(audience_id_str)

Parameters audience_id_str(str) – a string with pattern {platform}-{audience_id} e.g: "line-minhan_hgdfmjg2715".
```

Returns audience_id – a AudienceId obj

Return type [AudienceId](#)

```
class eyewitness.audience_id.AudienceRegister
Bases: object

Abstract Class for handling audience registration
```

```
insert_registered_user(audience_id, register_time, description)
abstract method for register audience id
```

```
register_audience(audience_id, meta_dict)
register audience
```

Parameters

- **audience_id**([AudienceId](#)) – audience information
- **meta_dict**(dict) – additional information

1.10 Feedback Msg Utils

Utils modules used for Feedback Msg

```
class eyewitness.feedback_msg_utils.FeedbackMsg(feedback_dict)
```

Bases: object

represent the Feedback msg

Parameters feedback_dict(dict) –

- **audience_id**: [AudienceId](#) the audience who feedback the msg
- **feedback_method**: str which kind of feedback
- **image_id**: [ImageId](#) the ImageId related to feedback
- **feedback_meta**: str misc feedback msg
- **feedback_msg_objs**: List[tuple] feedback objs (e.g. bboxes)
- **receive_time**: int the timestamp receive the msg

audience_id

AudienceId obj

Type [AudienceId](#)

```
feedback_meta
    feedback_meta str

    Type str

feedback_msg_objs
    List of msg named tuple objs

    Type List[tuples]

classmethod from_json(json_str)

    Parameters json_str(str) – feedback_msg json str

    Returns feedback_msg_obj – a feedback msg instance

    Return type FeedbackMsg

image_id
    ImageId obj

    Type ImageId

is_false_alert
    is false_alert or not

    Type bool

receive_time
    received timestamp

    Type int

to_json_dict()

    Returns image_dict – the dict representation of detection_result

    Return type dict

class eyewitness.feedback_msg_utils.FeedbackMsgHandler
    Bases: object

    Abstract class for FeedbackMsgHandler

    with a abstract method _handle(feedback_msg) used to handle feedback msg

feedback_method
    feedback_method

    Type str

handle(feedback_msg)
    a wrapper for _handle(feedback_msg) and feedback_method check
```

1.11 Handler Example

Handlers for detection results

1.11.1 DB Writer

```
class eyewitness.result_handler.db_writer.BboxNativeSQLiteDbWriter(db_path)
Bases: eyewitness.detection_utils.DetectionResultHandler, eyewitness.image_id.ImageRegister

Parameters db_path (str) – database path

create_db_table()
    create ImageInfo, BboxDetectionResult table if table not exist

detection_method
    BBOX

Type str

insert_detection_objs (image_id, detected_objects)
    insert detection results into db.

Parameters
    • image_id (str) – image_id
    • detected_objects (List[BoundingBoxObject]) – detected objects

insert_image_info (image_id, raw_image_path=None)
    insert image_info which used for unit-test

Parameters
    • image_id (str) – image_id
    • raw_image_path (str) – the path of raw image stored

update_image_drawn_image_path (image_id, drawn_image_path)
    update db image_id.drawn_image_path

class eyewitness.result_handler.db_writer.BboxPeeweeDbWriter(database,
                                                               auto_image_registration=False)
Bases: eyewitness.detection_utils.DetectionResultHandler, eyewitness.image_id.ImageRegister

Parameters
    • database (peewee.Database) – peewee db obj
    • auto_image_registration (Bool) – enable the auto_image_registration will check
        if image registered or not which might make the handle function more slowly

check_proxy_db()
    check if the db proxy is correct one, if not initialize again.

create_db_table()
    create ImageInfo, BboxDetectionResult table if table not exist

detection_method

insert_detection_objs (image_id, detected_objects)
    insert detection results into db.

Parameters
    • image_id (str) – image_id
    • detected_objects (List[BoundingBoxObject]) – detected objects
```

insert_image_info (*image_id*, *raw_image_path*=None)
insert image_info which used for unit-test

Parameters

- **image_id** (*ImageId* obj) – image_id obj (including channel, timestamp, file-format)
- **raw_image_path** (*str*) – the path of raw image stored

update_image_drawn_image_path (*image_id*, *drawn_image_path*)
update db image_id.drawn_image_path

class eyewitness.result_handler.db_writer.**FalseAlertPeeweeDbWriter** (*database*)
Bases: eyewitness.feedback_msg_utils.FeedbackMsgHandler, eyewitness.audience_id.AudienceRegister, eyewitness.image_id.ImageRegister

Parameters database (*peewee.Database*) – peewee db obj

check_proxy_db ()
check if the db proxy is correct one, if not initialize again.

create_db_table ()
create ImageInfo, RegisteredAudience, FalseAlertFeedback table if table not exist

feedback_method
feedback_method

Type str

insert_feedback_obj (*feedback_msg*)
insert feedback obj into db.

Parameters feedback_msg (*FeedbackMsg*) –

insert_image_info (*image_id*, *raw_image_path*=None)
insert image_info which used for unit-test

Parameters

- **image_id** (*str*) – image_id
- **raw_image_path** (*str*) – the path of raw image stored

insert_registered_user (*audience_id*, *register_time*, *description*)
insert image_info which used for unit-test

Parameters

- **audience_id** (*AudienceId*) –
- **register_time** (*int*) –
- **description** (*str*) –

1.12 ORM DB Models

orm models for Eyewitness with the support of peewee

1.12.1 ImageInfo

```
class ImageInfo(BaseModel):
    image_id = CharField(unique=True, primary_key=True)
    channel = CharField()
    file_format = CharField()
    timestamp = TimestampField()
    raw_image_path = CharField(null=True)
    drawn_image_path = CharField(null=True)
```

1.12.2 BboxDetectionResult

```
class BboxDetectionResult(BaseModel):
    image_id = ForeignKeyField(ImageInfo)
    x1 = IntegerField()
    x2 = IntegerField()
    y1 = IntegerField()
    y2 = IntegerField()
    label = CharField()
    meta = CharField()
    score = DoubleField()
```

1.12.3 RegisteredAudience

```
class RegisteredAudience(BaseModel):
    audience_id = CharField(unique=True, primary_key=True)
    user_id = CharField(null=False)
    platform_id = CharField(null=False)
    register_time = TimestampField()
    description = CharField()
```

1.12.4 FalseAlertFeedback

```
class FalseAlertFeedback(BaseModel):
    # peewee didn't support compositeKey as foreignKey, using field to specify field
    audience_id = ForeignKeyField(RegisteredAudience)
    image_id = ForeignKeyField(ImageInfo, null=True)
    receive_time = TimestampField()
    feedback_meta = CharField()
    # TODO: if the is_false_alert field needed??
    is_false_alert = BooleanField()
```

1.12.5 BboxAnnotationFeedback

```
class BboxAnnotationFeedback(BaseModel):
    # peewee didn't support compositeKey as foreignKey, using field to specify field
    audience_id = ForeignKeyField(RegisteredAudience)
    image_id = ForeignKeyField(ImageInfo, null=True)
    receive_time = TimestampField()
```

(continues on next page)

(continued from previous page)

```
feedback_meta = CharField()
is_false_alert = BooleanField()
x1 = IntegerField()
x2 = IntegerField()
y1 = IntegerField()
y2 = IntegerField()
label = CharField()
```

1.13 DataSet Utils

used to export the detected data which can be used for retrain/fine tune the model

```
class eyewitness.dataset_util.BboxDataSet (dataset_folder,  
                                         dataset_name,  
                                         valid_labels=None)
```

Bases: object

generate DataSet with same format as VOC object detections:

```
<dataset_folder>/Annotations/<image_name>.xml  
<dataset_folder>/JPEGImages/<image_name>.jpg  
<dataset_folder>/ImageSets/Main/trainval.txt  
<dataset_folder>/ImageSets/Main/test.txt
```

convert_into_darknet_format()

dataset_iterator (*with_gt_objs=True, mode='TEST_ONLY'*)

dataset_type

generate_train_test_list (*overwrite=True, train_ratio=0.9*)
generate train and test list

Parameters

- **overwrite** (*bool*) – if overwrite and file not exist will regenerate the train, test list
- **train_ratio** (*float*) – the ratio used to sample train, test list, should between 0~1

get_selected_images (*mode='TEST_ONLY'*)

get_valid_labels ()

ground_truth_iterator (*selected_images*)
ground_truth interator

Parameters mode (*str*) – the mode to iterate the dataset

Returns gt_object_generator – ground_truth_object generator, with first item if the ImageId

Return type Generator[*ImageId*, List[BoundedBoxObject]]

image_obj_iterator (*selected_images*)
generate eyewitness Image obj from dataset

Parameters mode (*str*) – the mode to iterate the dataset

Returns image_obj_generator – eyewitness Image obj generator

Return type Generator[*eyewitness.image_utils.Image*]

```

store_and_convert_darknet_bbox_tuples(dataset_file, selected_images, images_dir, labels_dir, label2idx, logging_frequency=100)

testing_set

training_and_validation_set

classmethod union_bbox_datasets(datasets, output_dataset_folder, dataset_name, filter_labels=None, remove_empty_labels_file=False)
    union bbox datasets and copy files to the given output_dataset

valid_labels
    the valid_labels in the dataset

eyewitness.dataset_util.add_filename_prefix(filename, prefix)

eyewitness.dataset_util.copy_image_to_output_dataset(filename, src_dataset,
                                                 jpg_images_folder,
                                                 anno_folder, file_fp, filter_labels=None, move_empty_labels_file=False)
    move annotation, jpg file from src_dataset to file destination, add prefix to filename and print to id list file

```

Parameters

- **filename** (*str*) – ori filename
- **src_dataset** ([BboxDataSet](#)) – source dataset
- **jpg_images_folder** (*str*) – destination jpg file folder
- **anno_folder** (*str*) – destination annotation file folder
- **file_fp** – the file pointer used to export the id list
- **filter_labels** (*Optional[set[String]]*) – used for filtering label for the destination dataset

```

eyewitness.dataset_util.create_bbox_dataset_from_eyewitness(database,
                                                       valid_classes, output_dataset_folder,
                                                       dataset_name)

```

generate bbox dataset from eyewitness requires:

- FalseAlertFeedback table: remove images with false-alert feedback
- BboxDetectionResult: get images with selected classes objects

```
eyewitness.dataset_util.generate_etree_obj(image_id, detected_objects, dataset_name)
```

Parameters

- **image_id** (*str*) – image_id as filename
- **detected_objects** – detected_objects obj from detected_objects table
- **dataset_name** (*str*) – dataset_name

```
eyewitness.dataset_util.parse_xml_obj(obj)
```

```

eyewitness.dataset_util.read_ori_anno_and_store_filtered_result(ori_anno_file,
                                                               dest_anno_file,
                                                               filter_labels, remove_empty_labels_file)

```

read the original annotation file, filter objects with valid labels export to the dest_anno_file

Parameters

- **ori_anno_file** (*str*) – original annotation file
- **dest_anno_file** (*str*) – destination annotation file
- **filter_labels** (*Optional[set[String]]*) – filter the labels
- **remove_empty_labels_file** (*bool*) – remove the image if it don't have obj

1.14 MOT Module

Modules related to MOT(multiple object tracking)

1.14.1 Video abstract

```
class eyewitness.mot.video.FilesAsVideoData(image_files, frame_shape=None,
                                             frame_rate=3)
Bases: eyewitness.mot.video.VideoData
frame_rate
frame_shape
n_frames
to_video(video_output_path, ffmpeg_quiet=True)

class eyewitness.mot.video.FolderAsVideoData(images_dir, file_template='*[0-9].jpg')
Bases: eyewitness.mot.video.FilesAsVideoData
frame_rate
frame_shape
n_frames

class eyewitness.mot.video.Mp4AsVideoData(video_file, ffmpeg_quiet=True,
                                           in_memory=True)
Bases: eyewitness.mot.video.VideoData
frame_rate
frame_shape
n_frames

class eyewitness.mot.video.VideoData
Bases: object
this class were used to represent a Video (List of Frames)
frame_rate
frame_shape
n_frames

eyewitness.mot.video.is_program_exists(program)
since the python-ffmpeg needs the host install ffmpeg first thus we need a method that can used to find executable
file exists
program: str the executable file to fine
is_file_exists: bool return the executable file exists or not
```

1.14.2 Tracker abstract

```
class eyewitness.mot.tracker.ObjectTracker
    Bases: object

track(video_data)

    Parameters video_data (VideoData) – the video data to be tracked

    Returns video_tracked_result – the tracked video result

    Return type VideoTrackedObjects
```

1.14.3 Evaluation

```
class eyewitness.mot.evaluation.VideoTrackedObjects
    Bases: collections.defaultdict

actually a VideoTrackedObjects object is a subclass of defaultdict with list and expected result were Dict[int, List[BoundingBoxObject]]

classmethod from_dict(tracked_obj_dict)

classmethod from_tracked_file(trajectory_file, ignore_gt_flag=False)
    parsed the trajectory file, and reuse the BoundingBoxObject class

    Parameters track_file (str) – the file path of object tracking ground_truth, format is
        <frame>, <id>, <bb_left>, <bb_top>, <bb_width>, <bb_height>, <conf>...

    Returns parsed_tracked_objects – key is the frame_idx, value is the objects detected in this
        frame and the label field in BoundingBoxObject were set as object_id

    Return type Dict[int, List[BoundingBoxObject]]

to_file(dest_file)

eyewitness.mot.evaluation.mot_evaluation(video_gt_objects, video_tracked_objects, thresh-
    old=0.5)
with the help of motmetrics we can evaluate our mot tracker

video_gt_objects: Dict[int, List[BoundingBoxObject]] ground_truth object of video, key is the frame_idx,
    value is the objects detected in this frame and the label field in BoundingBoxObject were set as object_id

video_tracked_objects: Dict[int, List[BoundingBoxObject]] predicted mot result of video, key is the
    frame_idx, value is the objects detected in this frame and the label field in BoundingBoxObject were set as
    object_id

summary: Dataframe the dataframe of evaluation result with the fields used in MOT2019 https://motchallenge.net/results/CVPR\_2019\_Tracking\_Challenge/
```

1.14.4 Visualize

```
eyewitness.mot.visualize_mot.draw_tracking_result(parsed_tracked_objects,
    color_list, video_obj, out-
    put_images_dir=None, out-
    put_video_path=None,
    n_trajectory=50, ffn-
    peg_quiet=True)
```

this method used to draw the tracked result back to original video notice that, if you want to export to output_video_path, you need to install it in your host, e.g. apt install ffmpeg

Parameters

- **parsed_tracked_objects** (*Dict[int, List[BoundingBoxObject]]*) – key is the frame_idx, value is the objects detected in this frame and the label field in Bounding-BoxObject were set as object_id
- **color_list** (*List[tuple[int]]*) – the color_list used to draw each object_id
- **video_obj** ([VideoData](#)) – the original video object
- **output_images_dir** (*Optional[str]*) – the dir used to stored drawn image, the stored template is Path(output_images_dir, "%s.jpg" % str(t).zfill(6)), t is current frame number
- **output_video_path** (*Optional[str]*) – the output path of video
- **n_trajectory** (*int*) – the number of previous point to be drawn
- **ffmpeg_quiet** (*bool*) – route the ffmpeg_quiet logging to stdout or not

Python Module Index

e

eyewitness.audience_id, 12
eyewitness.dataset_util, 18
eyewitness.detection_result_filter, 11
eyewitness.detection_utils, 10
eyewitness.evaluation, 12
eyewitness.feedback_msg_utils, 13
eyewitness.image_id, 7
eyewitness.image_utils, 8
eyewitness.mot.evaluation, 21
eyewitness.mot.tracker, 21
eyewitness.mot.video, 20
eyewitness.mot.visualize_mot, 21
eyewitness.object_detector, 10
eyewitness.result_handler.db_writer, 15

Index

A

add_filename_prefix() (in module eyewitness.dataset_util), 19
apply() (eyewitness.detection_result_filter.DetectionResultFilter method), 11
audience_id (eyewitness.feedback_msg_utils.FeedbackMsg attribute), 13
AudienceId (class in eyewitness.audience_id), 12
AudienceRegister (class in eyewitness.audience_id), 13

B

BboxDataSet (class in eyewitness.dataset_util), 18
BboxMAPEvaluator (class in eyewitness.evaluation), 12
BboxNativeSQLiteDbWriter (class in eyewitness.result_handler.db_writer), 15
BboxPeeweeDbWriter (class in eyewitness.result_handler.db_writer), 15

C

calculate_average_precision() (eyewitness.evaluation.BboxMAPEvaluator method), 12
calculate_label_ap() (eyewitness.evaluation.BboxMAPEvaluator method), 12
check_proxy_db() (eyewitness.detection_result_filter.FeedbackBboxDeNoiseFilter method), 12
check_proxy_db() (eyewitness.result_handler.db_writer.BboxPeeweeDbWriter method), 15
check_proxy_db() (eyewitness.result_handler.db_writer.FalseAlertPeeweeDbWriter method), 16
convert_into_darknet_format() (eyewitness.dataset_util.BboxDataSet method), 18

copy_image_to_output_dataset() (in module eyewitness.dataset_util), 19
create_bbox_dataset_from_eyewitness() (in module eyewitness.dataset_util), 19
create_db_table() (eyewitness.result_handler.db_writer.BboxNativeSQLiteDbWriter method), 15
create_db_table() (eyewitness.result_handler.db_writer.BboxPeeweeDbWriter method), 15
create_db_table() (eyewitness.result_handler.db_writer.FalseAlertPeeweeDbWriter method), 16

D

dataset_iterator() (eyewitness.dataset_util.BboxDataSet method), 18
dataset_type (eyewitness.dataset_util.BboxDataSet attribute), 18
detect() (eyewitness.object_detector.ObjectDetector method), 10
detected_objects (eyewitness.detection_utils.DetectionResult attribute), 11
detection_method (eyewitness.detection_result_filter.DetectionResultFilter attribute), 11
detection_method (eyewitness.detection_result_filter.FeedbackBboxDeNoiseFilter attribute), 12
detection_method (eyewitness.detection_utils.DetectionResultHandler attribute), 11
detection_method (eyewitness.object_detector.ObjectDetector attribute), 10
detection_method (eyewitness.result_handler.db_writer.BboxNativeSQLiteDbWriter attribute), 15

```

detection_method (eyewitness.attribute), 16
    ness.result_handler.db_writer.BboxPeeweeDbWriter feedback_objs (eyewitness.feedback_msg_utils.FeedbackMsg attribute), 14
DetectionResult (class in eyewitness.detection_utils), 10
DetectionResultFilter (class in eyewitness.detection_result_filter), 11
DetectionResultHandler (class in eyewitness.detection_utils), 11
draw_bbox () (eyewitness.image_utils.ImageHandler class method), 8
draw_tracking_result () (in module eyewitness.mot.visualize_mot), 21
drawn_image_path (eyewitness.detection_utils.DetectionResult attribute), 11

E
evaluate () (eyewitness.evaluation.Evaluator method), 12
evaluation_method (eyewitness.evaluation.BboxMAPEvaluator attribute), 12
evaluation_method (eyewitness.evaluation.Evaluator attribute), 12
Evaluator (class in eyewitness.evaluation), 12
eyewitness.audience_id (module), 12
eyewitness.dataset_util (module), 18
eyewitness.detection_result_filter (module), 11
eyewitness.detection_utils (module), 10
eyewitness.evaluation (module), 12
eyewitness.feedback_msg_utils (module), 13
eyewitness.image_id (module), 7
eyewitness.image_utils (module), 8
eyewitness.mot.evaluation (module), 21
eyewitness.mot.tracker (module), 21
eyewitness.mot.video (module), 20
eyewitness.mot.visualize_mot (module), 21
eyewitness.object_detector (module), 10
eyewitness.result_handler.db_writer (module), 15

F
FalseAlertPeeweeDbWriter (class in eyewitness.result_handler.db_writer), 16
feedback_meta (eyewitness.feedback_msg_utils.FeedbackMsg attribute), 13
feedback_method (eyewitness.feedback_msg_utils.FeedbackMsgHandler attribute), 14
feedback_method (eyewitness.result_handler.db_writer.FalseAlertPeeweeDbWriter attribute), 16

G
generate_etree_obj () (in module eyewitness.dataset_util), 19
generate_train_test_list () (eyewitness.dataset_util.BboxDataSet method), 18
get_selected_images () (eyewitness.dataset_util.BboxDataSet method), 18

```

get_valid_labels()
 ness.dataset_util.BboxDataSet
 18

ground_truth_iterator()
 ness.dataset_util.BboxDataSet
 18

H

handle() (eyewitness.detection_utils.DetectionResultHandler
 method), 11

handle() (eyewitness.feedback_msg_utils.FeedbackMsgHandle
 method), 14

I

Image (*class in eyewitness.image_utils*), 8

image_id (eyewitness.detection_utils.DetectionResult
 attribute), 11

image_id (eyewitness.feedback_msg_utils.FeedbackMsg
 attribute), 14

image_obj_iterator()
 ness.dataset_util.BboxDataSet
 18

ImageHandler (*class in eyewitness.image_utils*), 8

ImageId (*class in eyewitness.image_id*), 7

ImageProducer (*class in eyewitness.image_utils*), 9

ImageRegister (*class in eyewitness.image_id*), 7

insert_detection_objs()
 (eyewitness.
 ness.result_handler.db_writer.BboxNativeSQLiteDbWriter
 method), 15

insert_detection_objs()
 (eyewitness.
 ness.result_handler.db_writer.BboxPeeweeDbWriter
 method), 15

insert_feedback_obj()
 (eyewitness.
 ness.result_handler.db_writer.FalseAlertPeeweeDbWriter
 method), 16

insert_image_info()
 (eyewitness.
 ness.image_id.ImageRegister method), 8

insert_image_info()
 (eyewitness.
 ness.result_handler.db_writer.BboxNativeSQLiteDbWriter
 method), 15

insert_image_info()
 (eyewitness.
 ness.result_handler.db_writer.BboxPeeweeDbWriter
 method), 15

insert_image_info()
 (eyewitness.
 ness.result_handler.db_writer.FalseAlertPeeweeDbWriter
 method), 16

insert_registered_user()
 (eyewitness.
 ness.audience_id.AudienceRegister
 method), 13

insert_registered_user()
 (eyewitness.
 ness.result_handler.db_writer.FalseAlertPeeweeDbWriter
 method), 16

is_false_alert
 (eyewitness.
 ness.feedback_msg_utils.FeedbackMsg
 attribute), 9

(eyewitness-
 method), 14

is_program_exists() (in module eyewitness.mot.video), 20

M

mot_evaluation() (in module eyewitness.mot.evaluation), 21

Mp4AsVideoData (*class in eyewitness.mot.video*), 20

N

names (eyewitness.mot.video.FilesAsVideoData attribute), 20

n_frames (eyewitness.mot.video.Mp4AsVideoData attribute), 20

n_frames (eyewitness.mot.video.VideoData attribute), 20

O

ObjectDetector (*class in eyewitness.object_detector*), 10

ObjectTracker (*class in eyewitness.mot.tracker*), 21

P

parse_xml_obj() (in module eyewitness.dataset_util), 19

pil_image_obj (eyewitness.image_utils.Image
 attribute), 8

PostFilePathImageProducer (*class in eyewitness.image_utils*), 9

produce_image() (eyewitness.image_utils.ImageProducer
 method), 9

produce_image() (eyewitness.image_utils.PostBytesImageProducer
 method), 9

produce_image() (eyewitness.image_utils.PostFilePathImageProducer
 method), 9

produce_image() (eyewitness.image_utils.PostFilePathImageProducer
 method), 9

produce_method (eyewitness.image_utils.ImageProducer
 attribute), 9

produce_method (eyewitness.image_utils.PostBytesImageProducer
 attribute), 9

produce_method (eyewitness.image_utils.PostFilePathImageProducer
 attribute), 9

R

read_image_bytes() (eyewitness.image_utils.ImageHandler class method), 9

read_image_file() (eyewitness.image_utils.ImageHandler class method), 9
read_ori_anno_and_store_filered_result() (in module eyewitness.dataset_util), 19
receive_time (eyewitness.feedback_msg_utils.FeedbackMsg attribute), 14
register_audience() (eyewitness. audience_id.AudienceRegister method), 13
register_image() (eyewitness.image_id.ImageRegister method), 8
resize_and_stack_image_objs() (in module eyewitness.image_utils), 9

update_image_drawn_image_path() (eyewitness.result_handler.db_writer.BboxPeeweeDbWriter method), 16

valid_labels (eyewitness.dataset_util.BboxDataSet attribute), 19
valid_labels (eyewitness.object_detector.ObjectDetector attribute), 10
VideoData (class in eyewitness.mot.video), 20
VideoTrackedObjects (class in eyewitness.mot.evaluation), 21

S

save() (eyewitness.image_utils.ImageHandler class method), 9
store_and_convert_darknet_bbox_tuples() (eyewitness.dataset_util.BboxDataSet method), 18
swap_channel_rgb_bgr() (in module eyewitness.image_utils), 10

T

testing_set (eyewitness.dataset_util.BboxDataSet attribute), 19
to_file() (eyewitness.mot.evaluation.VideoTrackedObjects method), 21
to_json_dict() (eyewitness.detection_utils.DetectionResult method), 11
to_json_dict() (eyewitness.feedback_msg_utils.FeedbackMsg method), 14
to_video() (eyewitness.mot.video.FilesAsVideoData method), 20
track() (eyewitness.mot.tracker.ObjectTracker method), 21
training_and_validation_set (eyewitness.dataset_util.BboxDataSet attribute), 19

union_bbox_datasets() (eyewitness.dataset_util.BboxDataSet class method), 19
update_false_alert_feedback_bbox() (eyewitness.detection_result_filter.FeedbackBboxDeNoiseFilter method), 12
update_image_drawn_image_path() (eyewitness.result_handler.db_writer.BboxNativeSQLiteDbWriter method), 15